mmpEMAIL

## Windows 10 Mail Configuration

As a IMAP mail client for reading emails.

- 1. Open your Windows 10 Mail
- 2. Click on Accounts

Config 3 • IMAP



mm	pE/	MA	IL

3. Click on Add account



 $\times$ 

Config 3 • IMAP

4. Click on Advanced setup

**mmpEMAIL** 



Config 3 • IMAP

mmp	EMAIL Win	Mail		
		≡	Add an account	
5.	Click on " <b>Internet email</b> "	+ New mail	Advanced setup	
		우 Accounts	sure, check with your service provider.	
			Exchange ActiveSync Includes Exchange and other accounts that use Exchange ActiveSync.	
			Internet email POP or IMAP accounts that let you view your email in a web browser.	
		1		
		Berry .		
			Cancel	
Conf	ia 3 • IMAP 4/7	⊠ <u>≣</u> x <sup>A</sup>	(A)	

 $\times$ 

Enter: 6. Email address: Your email User name: Your email Password: Your password

**mmpEMAIL** 

Remark:



X

mmpEMAIL

Account name: Choose any name you want

Win

6/7

Send your message using this name: Choose any name you want

Incoming email server: mail.mmp.lu

Account type: IMAP4

Config 3 • IMAP

Mail	
	Add an account X
+ New mail	Internet email account
우 Accounts	Account name Pit Musterman es
	Send your messages using this name
	Incoming email server mail.mmp.lu
	Account type
	Outraina (CMTD) amail soniar
	Cancel Sign in
⊠ ඕ x <sup>A</sup>	(A)

 $\times$ 

mmpEMAIL

Win

7/7

7. Enter: Outgoing (SMTP) email server: **mail.mmp.lu** 

8. Select: Outgoing server requires authentication

Use the same user name and password for sending email

Require SSL for incoming email

Require SSL for outgoing email

9. Click on "Sign in"

		ante
	Add an account X	nts
New mail	Internet email account	edit settings.
Accounts	Account type	
recounts	IMAP4 V	es
	Outgoing (SMTP) email server	unt
	mail.mmp.lu ×	
	<ul> <li>Outgoing server requires authentication</li> <li>Use the same user name and password for sending email</li> <li>Require SSL for incoming email</li> <li>Require SSL for outgoing email</li> </ul>	
	Cancel Sign in	